

Where is Autoform DM installed?

Nicole Ojeda - 2022-11-10 - Comments (0) - Autoform DM FAQs

Autoform DM

These are the default install locations for key releases of DM which are displayed in the table below:

Windows Version	Java Version	DM Version	Location
Windows Server 2003/Windows XP	None	6.9	C:\Program Files\AutoFORM\PDM\Server\
		7.0	C:\Program Files\AutoFORM\PDM\Server 6.9.*\
		7.1	C:\Program Files\EFS Technology\PDM\Server_7.1.*\
		7.2	C:\Program Files\EFS Technology\AUTOFORM DM\Server_7.2.*\

Windows Version	Java Version	DM Version	Location
Windows Server 2008/Windows Vista	32-bit and 64-bit	6.9	C:\Program Files (x86)\AutoFORM\PDM\Server\
Windows Server 2012/Windows 8		7.0	C:\Program Files (x86)\AutoFORM\PDM\Server 7.0.*\
WindowsServer 2012R2/Windows 8.1		7.1	C:\Program Files (x86)\Formpipe Software\PDM\Server_7.1.*\
Windows Server 2016/Windows 10		7.2	C:\Program Files (x86)\Formpipe Software\Autoform DM\Server_7.2.*\
Windows 11		8.x	C:\Program Files\Formpipe Software\Autoform DM\Server_8.x.x
		9.x (Standalone)	C:\Program Files\Formpipe Software\Autoform DM\Server_9.x - [Node name]
		9.x (Cluster)	C:\Program Files\Formpipe Software\Autoform DM\Server_9.x - [Cluster name] - [Cluster role] - [Node name]
		10.x (Standalone)	C:\Program Files\Formpipe Software\Autoform DM\Server_10.x - [Node name]
		10.x (Cluster)	C:\Program Files\Formpipe Software\Autoform DM\Server_10.x - [Cluster name] - [Cluster role] - [Node name]

The version number (for example '7.0.') will be the version of DM you have installed. The paths may have been changed from their default paths during installation. You can find the location by looking at the "Path to executable" on the "Properties" of the DM Service in services.msc.

To view the DM system requirements, click [here](#).