

## CE connection forms script error

Alex Clemons - 2023-04-19 - Comments (0) - Lasetnet CE Connector General Information



Note

Before undertaking the solution to this error, users must create, modify and deploy a new CE solution. If this is not something that you are comfortable with, please refer the task to your CE system admin.

Due to a change in the way that Microsoft manages the forms in CE, there will be some errors in the setup forms for the CE Connector.

When opening the following forms:

- Lasetnet flyout/group
- Lasetnet group/HTTP Method
- Lasetnet group/OData Dialog
- Lasetnet group/OData Direct Submit
- Lasetnet group/Open URL

you may see the following error message:



This is due to the way the form is managing the default value for 'order'. There is a way to fix this error, which is to deploy a solution that updates the logic. Please follow the steps below:

### Create a solution containing the modifications

1. Navigate to **Settings** and select **Advanced Settings** from the dropdown menu.



1. On the Settings page, under Customization, select **Solutions**.



1. On the All Solutions page, click **New** to create a new solution.



1. Add values to the following fields:
  - **Display Name and Name:** Give the solution a sensible name and display name- these can be the same.
  - **Publisher:** Select the appropriate publisher (we have used the default publisher for the organisation).
  - **Version:** Set version as '1'.

The Configuration page field can be left blank. Click **Save**.



## Add the entities

1. Within the newly created solution, navigate to **Components > Entities** and then select **Add Existing**.



1. Add the following entities from the list:
  - Lasernet flyout/group

- Lasernet group/HTTP Method
- Lasetnet group/OData Dialog
- Lasetnet group/OData Direct Submit
- Lasetnet group/Open URL



You can multi-select entities in the list; the entries in the screenshot above are examples only.

1. Once the entries from Step 2 have been added, click **OK**.
2. Clear the **Include entity metadata** checkbox and only select the 'Main' Formtype for each selected entity.



1. Click **Next** and then **Finish** once the last entity has been configured.
2. Select **No, do not include required components**. Your solution will now look like this:



### **Change the value on the form**

1. Open the 'Main' form for the entity.



1. Click **Form Properties** in the ribbon.



1. Within Event Handlers, click **Edit** for the "Formpipe.Lasernet.DefaultValues.setDefaultValues"-function.



1. Change "lac\_order", "1" to "lac\_order", 1.



1. Click **OK** > **OK** and then **Save and Close**.

## **Publish**

1. Click **Save** and then select **Publish** in the ribbon.



1. Repeat for each form mentioned in this article:

- Lasernet flyout/group
- Lاسernet group/HTTP Method
- Lاسernet group/OData Dialog
- Lاسernet group/OData Direct Submit
- Lاسernet group/Open URL