

## How to change a user for the Lاسernet Service when using a LocalDB as the backend


Kate Coles - 2023-10-05 - Comments (0) - Lاسernet General Information

# Lاسernet

### Warning

We recommend that you only carry out this operation during system downtime or while Lاسernet is not in use, receiving no new input.

If you change the user on the service you will see this error in the Lاسernet Monitor:




```
Database location: 'C:\ProgramData\Formpipe Software\Lاسernet 10\Service\Default\Databases\Lاسernet Service.mdf'  
Detaching...  
Attaching and connecting...  
SAException(NativeCode=18456, Text=Login failed for user 'FORMPIPE\Flemming!'.  
Job Engine not started.  
Processing Started!
```

To correct this, follow these steps to get the LocalDB database attached to the new user:

1. Stop the **Lاسernet Service**.
2. Stop the **Lاسernet Config** service (if on the same server).
3. Start Windows **Taskmanager** and stop **sqlservr.exe** processes associated with LocalDB.
4. Right-click **Properties** to choose the right process.

In the example below, there are two associated processes with LocalDB (service and config), there is also one more process that is associated with the SQL Express install.



5. Clear all folders indicated in the following screenshot:



Note

- The Programdata folder might not be visible because it is hidden. In that case, type it in the search field.
- The databases folder only contains information including FailedJobs, ScheduledJobs, Pausejobs.
- There are no changes made to the Lasernet configuration. If you use SQL Server as a database for running jobs, delete or rename the database yourself using your preferred SQL tool.


6. Open **Services**, Locate the file and right-click it, the menu will then display. Select **Properties** from the list.

7. Change 'Log on as' to the new user, then start the **Lasernet Service** as this new user.

8. Start the **Lasernet Config** service (if on the same server).

9. Check that there are no errors within the **Lasernet Monitor** after starting the service.

You may need to select **Fetch newest**.



10. Reboot the server ensuring that the Lasernet Service starts before Lasernet Configurations (Config). Within the Lasernet Config 10 Properties, the service can be set to **Automatic (Delayed Start)**.

